Click to prove you're human



Password reset disk can be set with USB/CD/DVD, and can be used when you forget windows account password and can't login to computer, it's important and necessary 'cause we live in a world full of password. The article introduces 4 ways to create a windows password reset disk: UnlockGo (Windows) – help you when you have locked out of windows and create windows password reset disk in another accessible computer, Control Panel, Using your own disk and Offline NT tool. Method Supported Version Features UnlockGo (Windows) All new and old versions to Windows 11 Does not require current password and offers many other features too Control Panel Procedure is different for all versions of Windows Only works if you have the current password and user name Your Own USB Works for all versions of Windows If you don't know the password, you cannot use this method Offline NT Tool Not working for Windows 11 Uses the CMD and that's complicated for users Way 1. Password Reset Disk Windows 11/10/8/7/XP/Vista Free Download The ideal tool will be the one that allows the users to create a password reset disk without the current password and without logging in. UnlockGo – Windows Password Recovery offers the desired functionality without limitations and restrictions, creating a windows password reset disk in 1 click. With the newly created disk, you can reset or remove windows password and create or delete windows account with ease like a pro at home. How to Create a Password Reset Disk with UnlockGo (Windows)? Even if you don't have the current password for your Windows account, you can count on UnlockGo for Windows to help you. Here are the simple steps that you need to follow to create a password reset disk for Windows 10 or any other version using your own USB/CD/DVD. It will solve your problem like "I don't have a password reset disk and forget windows password, what should I do?" Download & Install UnlockGo (Windows) on another accessible computer if you locked out of computer, and then insert your USB/CD/DVD into it, one click to burn it. After seconds, your password reset disk has been created! Please be careful to choose the disk, and back up USB if there're important data stored on it. Burning process will format it. How to Use the Newly Created Password Reset Disk? Attach the USB to the locked computer and pressing F12, F8, F9, F10 or F11, depending upon the manufacturer to enter BIOS menu. Note: Surface BIOS Access Tips : Hold the volume-up button. Press and release the power button. When the Surface logo appears, release the volume-up button. Use the arrow keys to set reset USB as Boot Device Priority. And then set bootable USB/CD/DVD, last, press F10 to save and exit. If your computer running UEFI, select [UEFI: "your bootable disk name"]. as boot option #1. Your device will reboot and ask for windows system and select the target account to reset/remove password, or create/delete account as per your requirement. Note: After exiting BIOS menu your PC will reboot again, now you can start resetting Windows password. But Microsoft account password and RAID Server password can only be reset. Now, you've known everything about the windows password reset disk. Let's see how to create password reset disk in different situations. Way 2: Create Password Reset Disk on Control Panel after Logging In If you don't want a professional tool to create a reliable password reset disk, you can do this manually via the control panel. The process has the following steps to create a password reset disk windows 7 or any other version: Log in to your local account and open the control panel by pressing Windows Key+ X and then choose the user accounts option. Click on the "create a password reset disk" option from the left pane. Insert the USB or disk that you want to use to create a password reset disk and follow the path: click on the Next button >> select your USB or disk >> click Next >> enter a user name and password >> click Next and wait for a few minutes. You have created a password reset disk for Windows, and that disk can be used if you ever forget the Windows password. Way 3: Create a Password Reset Disk with Your Own USB with Password Windows 10 also allows the users to create a password reset disk by using their personal USB or any other storage disk. Here are the simple steps on how to create a password reset disk using your USB: Insert your SD card or USB to create a password reset disk. Press Windows Key + S and type user accounts in the search bar and click on user accounts. Click on create password reset disk and click on the Next button. Click on the drop-down menu and choose the name of your USB. Enter your user name and current password and click on the Next button. The process will take a few moments, and once the progress bar is at 100%, you can end the wizard and remove the successfully created password reset disk. Way 4: Create a Password Reset Disk with Offline NT Tool Free There are some tools that use a command line prompt to create a password reset disk, and this method can be pretty complicated for common users. Offline NT Password and Registry Editor is a tool that can be used to create a reset disk. What is a password reset disk? It is a backup password that can be used if you are locked out of your device. Here is the process to create a password reset disk with the Offline NT tool, downloaded from Offline NT tool. Download and install the latest release of the Offline NT tool from any authentic source. Download other additional files for USB or disk and unzip the additional downloaded files and copy them to your USB. Open CMD and type "j:syslinux.exe –ma j:" where 'j' indicates the name of the USB. Now, you can use this password reset USB to reset the password whenever locked out. This method may be suitable for the computer geeks but not for the common users. Summary Password reset disk can save you from big trouble if you are using the computer for personal or professional tasks. An authentic tool like UnlockGo for Windows can help you to get rid of complicated steps. Make sure to grab your copy of UnlockGo (Windows) and stop worrying about forgetting the password or losing data due to a forgotten password. Give it a try, and you won't regret your choice of the best tool to create a password reset disk. Lazesoft Recovery Suite is a very easy to use ALL-IN-ONE boot disk that repair your crashed Windows, recover data from deleted, formatted, damaged partition, clone or backup disk, reset your forgotten Windows password. Download | Order Now! A Windows password is the Windows password we use and type to log on our computer. We have to ensure that it is kept secured. Thus it is very important to make it complex so it won't be easy for others to determine it. There are times wherein we can forget our Windows password. What can we do then if this problem occurs? How can I retrieve or guess the password? How can I make a Windows password reset disk to reset Windows password. Well, you do not need to worry. The answers to these problems are as simple as ABC. If you want to make a Windows password reset disk that you can use to reset Windows password, you can create one by following the easy steps below: Open the Windows Control Panel Select User Accounts Click Create a password reset disk in the left pane. If you do not have available password reset disk and you need to reset your Windows password, I highly recommend our free Windows Password recovery software, Lazesoft Recover My Passoword Home Edition. What are the benefits you can get by using Lazesoft Recover My Passoword Home Edition? It is of High Quality since the software has 100% recovery rate and it is quite easy and comfortable to use. With the GUI interface and step by step wizard, you can easily reset your Windows administrator password even with little knowledge about computer. It is totally for FREE. The users are anytime free to recover password of Windows XP, Windows Vista, Windows 7 and Windows 8. There are easy steps to recover Windows administrator password using Lazesoft Recover My Passoword Home Edition. We have made them available for you. First is to locate other unlocked working computer to download, install and start Lazesoft Recover My Passoword Home Edition. Second is you need to Click to create a bootable CD or USB flash drive. Insert the newly burned CD or USB disk into the locked computer and then booting the locked computer from the new burned CD or USB disk, you have to follow the instructions on our product wizard to make your Windows administrator password blank. After all those instructions, you can log on your Windows administrator account without a password. The things that are must to perform the recovery process are the following: A stable internet connection, a working computer, a cd writer and a recordable CD or a USB flash drive. Lazesoft Recovery Suite is easy to use, powerful boot disk design to Recover Data, Recover crashed Windows System, Recover Windows Password, Clone or Backup Disk, etc. Download | Order Now! Find us on Facebook Find us on Twitter Watch Lazesoft Videos Step 3: Select target system in the list. Step 4: Choose the target account then click "Clear Password" to reset its login password. After reset successful, please restart your PC. Before restarting the computer, please disconnect the bootable USB/CD from your computer. Then your computer will boot normally. If the account you want to reset password for is Microsoft one, Renee Passnow will create another local account which has the similar name with the Microsoft one and preserve all the data inside. After reset successfully, please select the related local account on the login page. Also, you can click "Create new account" to make a new administrator to solve this problem with Renee Passnow. After Renee Passnow remove the password successfully, please disconnect the bootable media and restart PC. Then you can login your computer without password.Before trying the above methods, you could check the following tips:1. Whether the Caps Lock button is turned on. The login password is case sensitive. You may activate the Caps Lock carelessly, which could lead you to enter the wrong password.2. The Num Lock button is not activated. If your password is combined with numbers and characters, you may be notified the password is not correct if you do not active the Num Lock. Computer will not activate the "Num Lock" automatically when starting.3. Whether you use the Microsoft account.Tips for using the Reset Disk A password reset disk can be a lifesaver when you forget your password and are locked out of your computer. However, it is important to keep the reset disk safe and take certain considerations into account to protect your personal and sensitive information.First and foremost, it is crucial to choose a safe and secure location to store your password reset disk. It should be kept in a place where it is not easily accessible by anyone else. A safe or locked drawer can be a good option. Avoid leaving it in plain sight or in a common area where anyone can find it.It is also important to not label the reset disk with anything that might indicate its intended purpose. This means avoiding labels like "Password Reset" or "Master Key". Instead, opt for a cryptic label that only you can understand. This will help to keep the disk secure and prevent anyone else from guessing what it is for.Moreover, it is crucial to not use the reset disk for anything else besides resetting your password. Using it for other purposes may put your personal information at risk. You should also avoid connecting the reset disk to any unknown or untrusted computers.Another important consideration is to update the reset disk regularly. If you change your password or make any other changes to your account, it is important to create a new reset disk to reflect those changes.Finally, it is important to remember that a password reset disk is not the only option available for resetting your password. There are other methods, such as using a Microsoft account, which can also be used to reset your password. However, having a password reset disk as a backup is always a good idea, especially if you have sensitive or important files on your computer. Password Reset USB is a special type of media that can be used to reset Windows password. When you forgot Windows 11 password, password reset USB will help you unlock the computer in minutes without any data loss. This is a great tool for users as forgetting login password could be troublesome. In this tutorial we will review 5 different tools which can be used to create Windows 11 password reset USB. Pros and cons are included so that you can make an educated decision on choosing the correct tool for your situation. Forgotten Password Wizard Microsoft knows there are plenty of careless users out there who forgot Windows login password. Hence, it added a new feature called Forgotten Password Wizard since Windows 7. It is the stock utility for creating Windows password reset USB. Fortunately, this tool is still available on latest Windows 11. As soon as you have upgraded to Windows 11, or you purchase a new Windows 11 computer, the first step is to create a Windows 11 password reset disk to avoid any problematic situation related to passwords. This is a totally free tool and can be used without downloading any extra bit of software. Also, the USB will not be formatted. However, a password reset disk for computer A cannot be used on computer B. So, if you have not already prepared the disk and forgotten Windows 11 password, then this utility is not for you. How to create a password reset disk on Windows 11? Insert a blank USB flash drive into Windows 11 computer. It needs to have at least 8 GB free space. On Windows 11 desktop, open Control Panel app and navigate to User Accounts -> User Accounts. From the left sidebar, there is an option named Create a password reset disk. Click on it and this should bring up Forgotten Password Wizard, press Next to start creating a Windows 11 password reset disk for this local account. The USB drive is detected automatically by this tool. If it was the correct one, then click Next. If not, please choose the right one from drop-down list. Now it will ask you to enter your current password, type in the same and click Next. This should start the process of creating Windows 11 password reset disk. Once done, click on Finish button to complete the process and close password reset wizard. Go to USB drive and a new file (userkey.psw) was created on it. However, you can't open it as it is encrypted. Next time you forget Windows 11 password, boot from this Windows 11 password reset USB and launch Password Reset Wizard, follow the instructions on the screen to reset Windows 11 password for this specific local account. Pros: Available free on Windows 11. Easy to set up. Not formatting USB drive. Cons: Must know the current password of user account. Unable to reset password for another computer. Impossible to create one when the computer is locked. Can only create one on a Windows 11 computer. The above one is the most recommended way to create a Windows 11 password reset USB. However, it could not work if you forgot Windows 11 login password and unable to get into the desktop. Don't worry. There are a couple of very powerful third-party tools available for creating bootable Windows 11 password reset USB. SYSGeeker WinPassGo WinPassGo is a popular Windows 11 password reset USB creation tool developed by SYSGeeker. It is our first recommendation because it works like a charm and has a beautiful user interface, the same as Windows 11 stock Forgotten Password Wizard. You can create a Windows 11 password reset on a computer and use it to reset password for other computers. This is much better than previous suggestion. In addition, it also lets you create a new user account for login on the computer. It is very pleasant and straightforward process. The step-by-step tutorial is shown in the following: Download WinPassGo from their website and install it on a computer that works as normal. This can be any computer or even a Mac. Open the utility and insert the blank USB. Choose the right USB drive using drop-down menu and click on Burn icon at the right side. Wait 1-2 minutes and a Windows 11 password reset disk will be ready! Now, connect this password reset USB to any locked Windows 11 computer, boot from it and you will see password reset options. Finally, select an user account and reset the password in seconds. That's all! Pros: Simple and intuitive human user interface. Free trial available. Reset forgotten password on any Windows computer. Create new or delete old user accounts. Create a Windows 11 password reset USB in just 2 steps. Remarkable customer support. Built-in ISO burning tool. Cons: Modified-Win10PEX64 Windows Preinstallation Environment (PE) is a tailed version of full Windows OS. It is mostly used for system diagnosis and repair. Usually, a Windows PE contains a bundle of free software utilities for various purposes, such as data recovery, system backup, hardware checking and of course password recovery. Modified-Win10PEX64 is an upgraded version of stock Windows PE provided by Microsoft. You can use it to boot into a locked Windows 11 computer, and then take advantages of more than one hundred free tools that comes with this package. There are three free tools contained in this Windows PE for resetting Windows 11 password, including Active Password Changer and NTPWedit. Download Modified-Win10PEX64 ISO from AIO Boot website and Rufus from its respective website. The Modified-Win10PEX64 tool would be in the form of a ZIP file, unzip it and locate the ISO image file. After that, insert a blank USB flash drive in the computer. Now, fire up Rufus, select the USB from drop-down list in the Device section, click on SELECT to import the ISO file. Enter a meaningful volume name using the Volume label field. Finally, click on START to burn this ISO to USB drive. This will create a bootable Windows 11 password reset USB from Modified-Win10PEX64 ISO. Take out this password reset USB and use it to unlock any Windows computer that the password is forgotten. Simply boot from this USB and open Active Password Changer to reset Windows 11 password to blank on a locked computer. Pros: Packed with dozens of useful free tools to solve various problems. Two effective password reset programs available. Support Windows 11, Windows 10 and Windows 7. Compatible with UEFI boot. Cons: No longer update in future. No official support team or documentation available. Wait more time to download ISO file. Trinity Rescue Kit Trinity Rescue Kit is a live distribution of Linux OS. This rescue kit can be used to reset password for Windows 11, other Windows editions, and Linux too. It is freely available on their website, and the ISO image file can be easily downloaded. In addition to Windows password reset, it is also a handy tool for troubleshooting software and hardware issues, such as scanning virus, accessing SSH server, system backup and restore, analyzing hardware and resetting Windows password. How to use Trinity Rescue Kit for creating Windows password reset USB? Go and find another working computer. Then download Trinity Rescue Kit ISO file for the Trinity Rescue Kit from their website, along with Rufus. After that, attach a blank USB flash drive to that computer and run Rufus software. Next, select the USB name and import Trinity Rescue Kit ISO image. Don't forget to enter a meaningful volume name under Volume label field. Finally, click on START button to create a bootable USB from Trinity Rescue Kit ISO, which contains a Windows password resetting utility in it. After burning, a Windows 11 password reset USB is ready for use. Pros: Versatile utility to solve both software and hardware problems. Supports Windows 11, along with other editions of Windows and Linux. Free of cost. Cons: Only Command Line interface available. You need to complete the task by typing in commands. Some of the ISO Download links broken. The Bottom Line Now comes the hard part, which Windows 11 password reset USB creation tool should you use? If you could still login to Windows 11 computer, then go with the stock option on Windows 11. If not, then pick up WinPassGo since it is easy to use, does not require you to download any other tool to burn any ISO image file. Also, as an added advantage they have a support team available. With Windows Password Key, you can create a bootable CD/DVD/USB to reset forgot Windows password. Below is the detailed guide to do that.Step 1. Download and install Windows Password Key on any accessible computer.Step 2. Run Windows Password Key and choose CD/DVD/USB as your media type. Step 3. Insert a CD/DVD/USB and select the inserted CD/DVD/USB from drop-down list, then click "Begin burning" button. Step 4. After Windows password reset usb disk or cd/dvd disk burning, plug the created CD/DVD/USB into locked computer, and set computer boot from it. Step 5. After computer boots from CD/DVD/USB, select the locked computer Windows system and user, then click "Reset Password" to remove its password or reset it as "iSunshare@2012". Or you can click "Add User" button to create new administrator. After reboot your computer, you can access into your Windows again. While passwords are essential for protecting the privacy of your PC, forgetting them can be a frustrating experience, especially when trying to reset or recover them. When it comes to resetting passwords, many users seek guidance on creating and using password reset disks in online forums. A password reset disk is a useful feature that can help reset forgotten passwords on Windows. It can be created using a CD, USB, or other removable storage devices. In case you forget your Windows password, having a prepared password reset USB can assist you in resetting it. Additionally, once created, you do not have to create it again as it can be used indefinitely. By the way, the password we're talking about is a local account password, if you're using a Microsoft account to log in to your system, you can go to the password website to change it online. Why your Windows password reset USB can't be used on another PC? The advantage of using a password reset disk is that it provides a simple and efficient solution for resetting passwords without the need for additional software or technical expertise. However, it's important to note that the password reset disk should be created before you forget your password; otherwise, it won't be helpful. This is because the password reset disk includes information specific to that particular computer and user account, such as the security identifier (SID) and the user's password hash. The SID is a unique identifier assigned to each Windows installation, while the password hash is a scrambled version of the user's password that is stored in the system registry. These pieces of information are necessary to reset the password on the user account for that specific computer. Due to this specificity, a password reset USB created on one computer cannot be used on another computer or even the same computer with a different user account. Using the password reset USB on a different computer could cause compatibility issues and potentially damage the system, as it would not contain the necessary SID and password hash required for resetting the password. Windows 10 password reset USB free download/create If you often forget your password or change it frequently, then before you forget it, you can create a password reset USB via the built-in "Forgotten Password Wizard" to prevent forgetting your password in the future, or if the current password cannot log in to the computer system properly due to computer malfunction. And don't forget to reset the USB after you change a new PC password each time. Now, we'll show you how to create and use a Windows password reset USB for your Windows 10 local account. Part 1. Create Windows 10 password USB for current PC Step 1. Insert the target USB into the PC, and check whether it is detected by your PC. Step 2. Click "Start" to open the search bar, type "create password reset disk" and press "Enter" to open this function. Step 3. When the "Forgot Password wizard" window appears, click "Next" to continue the operation. Step 4. In the new window, choose the prepared USB and click "Next". Step 5. Then enter the current password and select "Next". Step 6. When the password reset USB is created, click "Next". If you forget your current password, the password reset USB can immediately help. Part 2. Use Windows 10 reset password USB on the current PC If you forget your current password, the password reset USB can immediately help. Step 1. Insert the password reset USB, then click "Reset password". Step 2. The Password Reset Wizard will pop out, click "Next". Step 3. In the new window, you will be asked to choose the password reset disk, then click "Next". Step 4. Input the new password and the new password hint, then click "Next". Step 5. When you see the following interface, click "Finish". Easily create a Windows password reset USB for any PC As we've explained clearly, the password reset USB created via Windows built-in password reset wizard could only be used on the same computer since it includes information specific to that particular computer and user account. If you haven't made one before everything is too late, then all is in vain. So, to avoid this embarrassing situation, you have another choice: using a professional password reset tool to create a widely used Windows password reset USB. AOMEI Partition Assistant Professional is a disk and partition manager for all Windows PC systems. The "Reset Password" utility of this tool allows users to use USB/CD/DVD on any running Windows PC to create a Windows password reset USB which can be used on any Windows computer without system limitations. And it also has many other handy functions to help you monitor disk status and fix common PC problems like crowded C drive, MBR/GPT safe conversion, disk clone, app moving, etc. After you find another running Windows PC and prepare an empty USB, we can start our work. Step 1. Insert the target USB into the PC, download and run AOMEI Partition Assistant Professional, and click "Tools"> "Reset Password". Step 2. A small window will be popped, click "Next". Step 3. You need to choose "General USB Flash Disk" and click "Proceed". Since the target USB will be formatted, all data will be deleted, so please back up the important data before this operation. Step 4. Read the popped information carefully, then click "Yes". Step 5. Wait patient, when the password reset USB is created, click "Finish". Step 6. Take out the USB and insert it into the locked PC, then restart it. You'll be asked to change the boot drive, then boot the PC from the USB, select the Windows system, and click "Next". Step 7. All accounts on the PC will be shown in the interface, click the target account, tick "Remove Account Password" or "Reset Account Password", then click "Next". Step 8. If you select "Reset Account Password", you can set the new password and then click "Yes". If you select "Remove Account Password", please follow the wizard to remove it. Verdict A Windows 10 password reset USB can save you when you forget the password, but if you're wishing to create it via the built-in password reset wizard, you need to do it previously. However, with AOMEI Partition Assistant, you can create a password reset disk without any limits. In addition, this tool also has the Server Edition and other higher editions, if you want to use it to fix problems on Windows Server computers or for enterprise usage, you can choose the matched edition according to your case. We use cookies for personalizing content and ads and providing social media features. Your usage information on our website will be used for social media, advertising, and traffic analytics, or shared with our partners. Clicking "Accept" means you agree to use our cookies . Passwords are essential for protecting your computer privacy, but forgetting them can be frustrating. When it comes to resetting passwords, many users look to forums for guidance on creating and using a password reset disk. In this article, EaseUS will provide a free Windows 10 password reset disk download and how to create it. Before that, you need to know some hints in advance: You need to make a password reset disk that is suitable for your current computer before forgetting your password. If your computer/PC is locked, the password reset disk won't work. You don't have to create a new password reset disk when changing your password, even if you change it multiple times. A password reset disk created this way will only work with the computer you are currently using, as it will contain information specific to that particular computer and user account. If you want to create a bootable disk for another computer, skip to the next section. To create a Windows 10 Password Reset USB for any PC, turn to EaseUS Partition Master. This Windows password unlocker breaks all the limits above, and its "Password Reset" feature allows you to create a Windows 10 Password reset disk and crack Windows password for any locked PC. It is easier to use than the Windows built-in tools. You can skip to Part 3 to learn how to use it to create a Windows password reset USB or disk. Free Download Windows 11/10/8/7100% Secure Windows 10 Password Reset USB Free Download/Create A password reset disk is available to help reset forgotten passwords on Windows. It can be created using a CD, USB, or other removable storage device. When you forget your Windows 10 password, a password reset USB or disk can help you reset it. Furthermore, once created, you do not have to create it again, as it can be used indefinitely. This guide is from Microsoft, so you can feel free to follow it. Further Reading: Reset Windows 10 Password with USB Now let's learn how to download and make a Windows 10 password reset disk: 1. Insert the USB flash drive into your PC. NOTE: Creating a password reset disk will not reformat your USB flash drive, but you'd better back up all the data on it just in case something unexpected happens. 2. In the search box on the Windows 10 taskbar, type create password reset disk and select Create password reset disk. 3. In the Forgot Password wizard, click Next. Select the correct USB flash drive and select Next. Further Reading: How to Know the Current Password One Last Time 4. Enter your current password and select Next. When the wizard completes, select Finish. 5. Remove the USB flash drive and store it in a safe location. How to Use Password Reset USB on Current PC If you forget the current password, you can simply find the password reset disk you created and insert it into your computer. It can help immediately. You can share this guide to help more users who don't know how to use a password reset disk on a PC. Step 1. Insert the password reset USB disk you made and click "Reset Password." Step 2. The Password Reset Wizard window will pop up. Click "Next". Step 3. In the new window, you will be asked to select the correct password reset disk and click "Next." Step 4. Enter the new password and new password prompt, and click "Next." Step 5. When you see the following interface, click "Finish". Read Also: Create Windows 10 Password Reset USB for All PCs However, a password reset USB created through the Windows built-in Password Reset Wizard can only be used on the same computer because it contains information specific to that particular computer and user account. And if you have forgotten your password, your efforts will be in vain. Fortunately, you have another option: use a professional password reset tool to create a widely used Windows password reset USB flash drive. EaseUS WinRescure is a disk and partition manager suitable for all Windows PC systems. Its "Reset Password" feature allows users to create a Windows password reset USB using USB/CD/DVD on any PC running Windows. The most important is. This USB can be used on any Windows computer without restrictions. Free Download Windows 11/10/8/7100% Secure Step 1. Connect the USB drive/external drive to a working computer, open EaseUS WinRescuer, and click "Create Bootable Media." Step 2. Select EaseUS Boot Toolkits and other components you need. Then, click "Next." Step 3. Select your movable device and click "Go" to create an image on your USB drive/external drive. Step 4. Before making the bootable media, you will receive the warning message: data will be erased. Click "OK" to confirm. Step 5. Connect the created bootable drive to the faulty computer and reboot it by pressing and holding "F2"/"Del" to enter the BIOS. Then, set the WinPE bootable drive as the boot disk and press "F10" to exit. Step 6. Then, the computer will enter WinPE desktop. Find and launch Password Reset. Step 7. Select your Windows version and choose the Windows account you want to reset. Step 8. When this prompts, click "Confirm" to continue resetting your Windows password. Step 9. Wait patiently, and you will receive an message that the password has been changed successfully. Click "OK" to complete the password reset process. Free Download Windows 11/10/8/7100% Secure Don't miss this utility. This tool can not only create a bootable USB password reset tool but also do the following tasks: Unlock Lenovo Laptop Without Password Unlock Dell Laptop Without Password You can also follow the video and reset Windows password without data lost. Conclusion Windows 10 Password Reset USB is very helpful when you forget your password, but you need to do this beforehand if you are creating a password reset disk through the built-in password reset wizard. However, EaseUS Partition Master allows you to create a password reset disk without restrictions. You can share this convenient tool with more people. Windows 10 Password Reset USB FAQs Do you know how to download or create Windows 10 Password Reset USB now? If you have further questions, check the questions and answers below. 1. How to reset your Windows 10 password with a USB flash drive free? To reset your Windows 10 password with a USB flash drive, make sure you have created or downloaded a Windows 10 password reset disk/USB. Follow these steps to try: 1. Insert the password reset USB flash drive into your PC. 2. In the search box on the Windows 10 taskbar, type 'create password reset disk' and select Create password reset disk. 3. In the Forgot Password wizard, click Next to continue. Select the correct USB flash drive and click Next. 4. Enter your current Windows password and click Next. When the wizard completes, click Finish. Then, when you forget your Windows password, connect the USB flash drive to your PC. 2. Is there a free Windows 10 password reset tool? Yes. Windows comes with a feature called 'Create password reset disk,' which allows you to reset your Windows 10 passwords for free. However, this feature has limits: The Windows 10 password reset disk needs to be created before you forget the password. This password reset disk can only work on the computer where you created the reset disk. If you want to break the limit, turn to a reliable third-party software - EaseUS Partition Master. 3. How to create a password recovery USB flash disk in Windows 10? Follow these steps to create a password reset USB on Windows 10: 1. Connect the USB flash drive to your PC. 2. Type create password reset disk in the search box and select Create password reset disk. 3. Click Next in the Forgot Password wizard. Choose the correct USB flash drive and select Next. 4. Enter your current password and hit Next. Wait for the creation process to finish. Forgot Windows password? The simplest way to reset a forgotten password is by using a previously created password reset disk. You can create such disk on a USB removable media in Windows Control Panel. The problem is that you have to create the password reset disk before you forgot Windows password. Also, the password reset disk can only be used to reset password for a specific Windows account, it is unable to reset other account passwords on the same Windows installation, not to mention using it to unlock password on another computer. So how to reset your forgotten Windows password if you don't have such a password reset disk? Obviously you have to find some other ways to unlock your computer. Here we're going to show you how to create a bootable Windows password reset disk and then use it to remove your forgotten password. It can be used to reset Windows password for any user account on any computer. Part 1: How to Create a Bootable Windows Password Reset Disk If you've forgotten Windows password or be locked out of your account, you need to create a bootable Windows password reset disk on another computer. Download the zip archive of PCUnlocker utility. Unzip the download file which contains an ISO image: pcunlocker.iso. Insert a blank CD or USB flash drive into the computer. Burn the ISO image file to your CD or USB flash drive using ISO2Disc software. You can also create the disk with your favorite CD and DVD burning tools. The bootable Windows password reset disk is now ready for use. Part 2: How to Use Windows Password Reset Disk Once you've successfully created a bootable Windows password reset disk, you can use it to reset forgotten Windows admin/user passwords on any computer. Follow the steps: Insert the bootable Windows password reset disk into your locked computer. Change the boot device order in the BIOS so your computer will boot from Windows password reset CD or USB flash drive. After a while the bootdisk will launch the PCUnlocker utility. It automatically finds your Windows SAM database and display a list of Windows accounts inside it. Choose a Windows account whose password you want to reset, then click Reset Password button. It will remove your forgotten password instantly. Remove the password reset disk and restart the computer, you can then log on Windows with a blank password. With the bootable Windows password reset disk you can easily reset forgotten Windows password on Windows 10/8/7/Vista/XP (both 32-bit and 64-bit operating system). Buy PCUnlocker Professional Download PCUnlocker